Church Webcast:

Click here to access the Church's webcast system.

An individual must have the following in order to be able to schedule and manage events for their stake:

Church Account - Click here to create a Church account if needed.

Required Calling/Assignment - Stake clerk, stake technology specialist, or assistant stake technology specialist.

When accessing the portal for the first time, you will be asked to agree to the end user agreement and complete the setup wizard.

How To Schedule Church Webcast Stream

1. Go to webcast.churchofjesuschrist.org
2. Login using your Church account
3. If not already done, associate buildings in your stake the webcast org by clicking 


    a. Add locations available under "Org Locations" or create a custom location by clicking  next "Save Locations".
4. Once you have added your locations, close the location window.
5. **Optional:** If not already done, add a Teradek(s) encoder by clicking 

.
6. Click 

7. Fill-in the fields to complete the scheduling process:
    a. Required Fields:
        i. Event Name
        ii. Event Date
        iii. Start Time
        iv. Duration
        v. Time Zone
        vi. Broadcast Site – this is the location referenced in step 3. You need defined locations in order to schedule.
        vii. Broadcast Type
        viii. Nearest Region
    b. Optional Fields:
        i. Presiding Authority
        ii. Private Event – by selecting this viewers will need to login with their Church account **and** event code. By default events are "public" which only asks viewers to type in their name before viewing the event.
        iii. Test Event
        iv. High Bandwidth Encode – by default the system allows streams up to 2.1Mbps. High bandwidth encode will support up to 5Mbps.
        v. Large Event – No longer required. Will be removed soon.
        vi. Low Bandwidth Broadcast - No longer required. Will be removed soon.

8. Click

The event is now scheduled and you should see the “Event Card” (image below) in the portal.



Viewing Details

1. Click 

2. Under viewing links will be provided under the Viewing URL tab.
    a. **Home viewers** should receive the “General Viewing Link”. This is the same for every event scheduled.
    b. **Large groups viewing** the broadcast can be given the “Congregational Link”. Viewers using this link will need to login with their Church account and event code regardless if the event is public or private.
    c. **Event Code** this is provided only to viewers who are trying to watch a private event or connect with the congregational link.

Streaming Information

If streaming using a software encoder on the laptop (OBS), a cell phone app (Larix), or an encoder hardware (Teradek) you will need to configure the service/hardware with the required streaming information (RTMP). This information is found under 

on the event card and the “Teradek Manual Setup” or “Other Setup” tabs.

The RTMP stream information provided is the RTMP URL and stream key. Some products will require this information to be entered in separate fields and others will want it combined, usually separated with a forward slash (/). Check configuration instructions for the encoding solution selected for information on how to enter stream details.